

Rsam Platform Time Zone Correction Utility

Document Version: 10 | June 2020

© 2022 Relational Security Corporation dba Galvanize. All rights reserved. www.wegalvanize.com

Contents

About this Guide	.3
Using the Time Zone Conversion Utility	.4
Prerequisites	4
Executing the Utility	4
Notes on the Conversion Process	5

About this Guide

This document provides instructions for using the Rsam Time Zone Correction Utility to correct the date-time and time values of the erroneous records in the Rsam database.

This guide is intended to be used by Rsam Administrators or those users responsible for maintaining Rsam in customer environments.



Using the Time Zone Conversion Utility

Prerequisites

The prerequisites to using the Time Zone Conversion Utility are as follows:

- 1. Stop the Rsam Scheduler service before running this utility and restart the service once the utility has completed the execution successfully. This ensures that the date & time values related to Scheduler tables are updated correctly.
- 2. Obtain the utility from Rsam Technical Support.
- 3. Extract the contents of the folder, TimeZoneCorrectionUtility.zip.
- 4. Execute the **DB_Script.sql** file in your Rsam database.
- 5. Create a **distweb.dat** file with the following account credentials.
 - db_datareader
 - db_datawriter
 - public
 - rsam_client
 - db_ddladmin or db_owner (as admin privileges are required to run the utility and create backup tables)
- 6. Copy the newly created **distweb.dat** file into the **TimeZoneChangeUtility** folder.
- 7. Copy the **datasource.ini** from the application server into the **TimeZoneChangeUtility** folder.
- 8. Ensure the file **TIMEZOME_CHANGE_UTILITY_TABLES.csv**, which is located in the folder **CSVPath**, has the appropriate data.
 - By default, the CSV file will contain all the tables with date-time fields. If you want add a new table, you can add it after the last row in the file. Use the same format to add a row: ID, TABLE_NAME, IDENTITY_COLUMN_NAME, STATUS, LAST_UPDATED_IDENTITY.
 - Ensure all the entries in the STATUS column are **pending** and all the entries in the LAST_UPDATED_IDENTITY column are **0**.

Executing the Utility

To execute the Rsam Time Zone Conversion Utility, perform the following steps:



1. Right-click the **TimeZoneCorrectionUtility.exe** and select **Run as Administrator**. The **Time Zone Conversion for RSAM Tables** dialog box appears

Time Zone Conversion for RSAM Tables Select a CSV File							
Image: Supervised and the standard							
TABLE_NAME	COLUMN_NAME	STATUS					
ATTRIBUTETYPE	ATTTYPE_ENABLED_REDLINING_DATE/ATTTYPE_DEFAULT_VALUE	Completed					
FILE_FIELD	BFILE_DOE	Completed					
FI_FINDING_ATTRIBUTE	ATTRIBUTE_DATE	Completed					
GR	GR_DOE	Completed					
OBJECT_ATTRIBUTE	ATT_DATE	Completed					
RA_EVENTHANDLER_ACTION	ACTION_STRING	Completed					
RA_EVENTHANDLER_CRITERIA	CRITERIA_STRING	Completed					
SC_SCHEDULE	BEGIN_DATEIEND_DATE	Completed					
SC_TASK	LAST_RUNINEXT_RUN	Completed					
SYS_USER	USER_LAST_LOGIN USER_LAST_PASSWORD_CHANGE	Completed					
SYS_USER_LOOKUP_HISTORY	SYS_USER_LKP_HIST_DOE	Completed					
Processing Table :							
	Start Conversion	Exit					

2. In the **Destination Time zone** field, select the time zone value identical to the actual database time zone.

The **Source Time Zone** value is auto-selected to the time zone value saved in the Rsam Options field, **Database Timezone**.

Note: The information related to the tables on which the conversion must run is obtained by the utility from the file – **TIMEZOME_CHANGE_UTILITY_TABLES.csv**. For more information, see <u>this section</u>.

3. Click **Start Conversion** to start converting the date-time and time values for the tables listed in the CSV file, in the incorrect records.

On successfully converting the date-time and time attribute values, the status updates to **Completed** against each table name.

4. In case of any errors, refer the log file created in the **Logs** folder in the **TimeZoneCorrectionUtility** folder.

Notes on the Conversion Process

When the utility runs, the sequence of steps happening in the background are as follows:

- The utility creates a backup of the data in the specified tables, before converting the values. The name of the backup tables created will be in format –

 the specified tables, before converting the values. The name of the backup tables created will be in format –

 CableName>_Backup. This can be used to validate/ verify the conversion.
- The information related to the tables on which the conversion must run is obtained by the utility from the file – TIMEZOME_CHANGE_UTILITY_TABLES.csv, which is located in the folder – CSVPath.



- 3. If the conversion is successful, value in the column **Status** (highlighted in following screenshot) will be changed from **pending** to **Completed**.
- 4. In case of any error, value in the column **Status** will be changed from **pending** to **error**. The errors will be logged in the file available in the **Logs** folder.
- 5. After resolving the errors, on re-executing of the utility, the conversion will continue for tables with status **error**.
- If you want to re-execute the utility on tables with status Completed, update the status column for the required tables to pending and re-run the utility. The conversion will continue from the LAST_UPDATED_IDENTITY column value, for all records created after this identity value.

	Α	В	С	D	E	F
1	ID	TABLE_NAME	IDENTITY_COLUMN_NAME	COLUMN_NAME	STATUS	LAST_UPDATED_IDENTITY
2	1	ATTRIBUTETYPE	ATT_TYPE_ID	ATTTYPE_ENABLED_REDLINING_DATE ATTTYPE_DEFAULT_VALUE	pending	0
3	2	GR	GROUP_ID	GR_DOE	pending	0
4	3	FI_FINDING_ATTRIBUTE	FINDING_ATTRIBUTE_ID	ATTRIBUTE_DATE	pending	0
5	4	OBJECT_ATTRIBUTE	OBJ_ATT_ID	ATT_DATE	Pending	0
6	5	FILE_FIELD	BFILE_FIELD_ID	BFILE_DOE	pending	0
7	6	RA_EVENTHANDLER_ACTION	EVENTHANDLER_ACTION_ID	ACTION_STRING	pending	0
8	7	RA_EVENTHANDLER_CRITERIA	EVENTHANDLER_CRITERIA_ID	CRITERIA_STRING	pending	0
9	8	SC_TASK	TASK_ID	LAST_RUN NEXT_RUN	pending	0
10	9	SC_SCHEDULE	SCHED_ID	BEGIN_DATE END_DATE	pending	0
11	10	SYS_USER	USER_IDENT	USER_LAST_LOGIN USER_LAST_PASSWORD_CHANGE	pending	0
12	11	SYS_USER_LOOKUP_HISTORY	SYS_USER_LKP_HIST_ID	SYS_USER_LKP_HIST_DOE	pending	0